

## Quassel IRC - Bug #1158

### Crash after entering core password

04/28/2012 09:19 PM - kitterma

<b>Status:</b>	New	<b>Start date:</b>	04/28/2012
<b>Priority:</b>	Normal	<b>Due date:</b>	
<b>Assignee:</b>		<b>% Done:</b>	0%
<b>Category:</b>	Quassel Client	<b>Estimated time:</b>	0.00 hour
<b>Target version:</b>		<b>OS:</b>	Linux
<b>Version:</b>	0.8-pre		

**Description**

Application: quasselclient (v0.8.0 (dist-5988f4c))  
KDE Platform Version: 4.8.2 (4.8.2)  
Qt Version: 4.8.1  
Operating System: Linux 3.2.0-24-generic-pae i686  
Distribution: Ubuntu 12.04 LTS

-- Information about the crash:  
Laptop had just resumed. For some reason the password for my core wasn't stored, so I entered the password manually and the client immediately crashed.

The crash does not seem to be reproducible.

-- Backtrace:  
Application: Quassel IRC (quasselclient), signal: Segmentation fault  
Using host libthread\_db library "/lib/i386-linux-gnu/libthread\_db.so.1".  
[Current thread is 1 (Thread 0xb46d0a80 (LWP 2027))]

Thread 3 (Thread 0xb1f01b40 (LWP 2033)):  
#0 0xb5a6edcd in clock\_gettime () from /lib/i386-linux-gnu/librt.so.1  
#1 0xb72e7315 in do\_gettime (frac=0xb1f00f70, sec=0xb1f00f68) at tools/qelapsedtimer\_unix.cpp:123  
#2 qt\_gettime () at tools/qelapsedtimer\_unix.cpp:140  
#3 0xb73d1226 in QTimerInfoList::updateCurrentTime (this=0xb1602074) at kernel/qeventdispatcher\_unix.cpp:343  
#4 0xb73d157a in QTimerInfoList::timerWait (this=0xb1602074, tm=...) at kernel/qeventdispatcher\_unix.cpp:450  
#5 0xb73cfe23 in timerSourcePrepareHelper (src=<optimized out>, timeout=0xb1f0107c) at kernel/qeventdispatcher\_glib.cpp:136  
#6 0xb73cfebd in timerSourcePrepare (source=0xb1602040, timeout=<optimized out>) at kernel/qeventdispatcher\_glib.cpp:169  
#7 0xb59b8762 in g\_main\_context\_prepare () from /lib/i386-linux-gnu/libglib-2.0.so.0  
#8 0xb59b8f6f in ?? () from /lib/i386-linux-gnu/libglib-2.0.so.0  
#9 0xb59b91c1 in g\_main\_context\_iteration () from /lib/i386-linux-gnu/libglib-2.0.so.0  
#10 0xb73d08e7 in QEventDispatcherGlib::processEvents (this=0xb1600468, flags=...) at kernel/qeventdispatcher\_glib.cpp:426  
#11 0xb739c50d in QEventLoop::processEvents (this=0xb1f01200, flags=...) at kernel/qeventloop.cpp:149  
#12 0xb739c7a9 in QEventLoop::exec (this=0xb1f01200, flags=...) at kernel/qeventloop.cpp:204  
#13 0xb728594c in QThread::exec (this=0xb95e4ed0) at thread/qthread.cpp:501  
#14 0xb7379b5d in QNotifyFileSystemWatcherEngine::run (this=0xb95e4ed0) at io/qfilesystemwatcher\_inotify.cpp:248  
#15 0xb7288de0 in QThreadPrivate::start (arg=0xb95e4ed0) at thread/qthread\_unix.cpp:298  
#16 0xb5a90d4c in start\_thread () from /lib/i386-linux-gnu/libpthread.so.0  
#17 0xb5b8face in clone () from /lib/i386-linux-gnu/libc.so.6

Thread 2 (Thread 0xb0bffb40 (LWP 2036)):  
#0 0xb751b424 in \_\_kernel\_vsyscall ()  
#1 0xb5b81380 in poll () from /lib/i386-linux-gnu/libc.so.6  
#2 0xb59c6a3b in g\_poll () from /lib/i386-linux-gnu/libglib-2.0.so.0  
#3 0xb59b906e in ?? () from /lib/i386-linux-gnu/libglib-2.0.so.0  
#4 0xb59b952b in g\_main\_loop\_run () from /lib/i386-linux-gnu/libglib-2.0.so.0  
#5 0xb4db60ea in ?? () from /usr/lib/i386-linux-gnu/libgio-2.0.so.0  
#6 0xb59dc673 in ?? () from /lib/i386-linux-gnu/libglib-2.0.so.0  
#7 0xb5a90d4c in start\_thread () from /lib/i386-linux-gnu/libpthread.so.0  
#8 0xb5b8face in clone () from /lib/i386-linux-gnu/libc.so.6

Thread 1 (Thread 0xb46d0a80 (LWP 2027)):  
[KCrash Handler]  
#7 0xb7325234 in operator int (this=<error reading variable: Cannot access memory at address 0x4>) at

../include/QtCore/../../src/corelib/global/qglobal.h:2297  
#8 QIODevice::isOpen (this=0x0) at io/qiodevice.cpp:508  
#9 0xb77236a9 in SignalProxy::writeDataToDevice (dev=0x0, item=..., compressed=false) at /build/builddd/quassel-0.8.0/src/common/signalproxy.cpp:837  
#10 0xb76c94e8 in CoreConnection::loginToCore (this=0xb93d4d28, prevError=...) at /build/builddd/quassel-0.8.0/src/client/coreconnection.cpp:606  
#11 0xb76ca1d6 in CoreConnection::connectionReady (this=0xb93d4d28) at /build/builddd/quassel-0.8.0/src/client/coreconnection.cpp:579  
#12 0xb76ca3b5 in CoreConnection::sslSocketEncrypted (this=0xb93d4d28) at /build/builddd/quassel-0.8.0/src/client/coreconnection.cpp:540  
#13 0xb76f1916 in qt\_static\_metacall (\_a=0xbfbfd3080, \_id=57, \_o=0xb93d4d28, \_c=<optimized out>) at /build/builddd/quassel-0.8.0/obj-i686-linux-gnu/src/client/moc\_coreconnection.cxx:229  
#14 CoreConnection::qt\_static\_metacall (\_o=0xb93d4d28, \_c=QMetaObject::InvokeMetaMethod, \_id=57, \_a=0xbfbfd3080) at /build/builddd/quassel-0.8.0/obj-i686-linux-gnu/src/client/moc\_coreconnection.cxx:164  
#15 0xb73b46b1 in QMetaObject::activate (sender=0xb963efb8, m=0xb674ad78, local\_signal\_index=0, argv=0x0) at kernel/qobject.cpp:3547  
#16 0xb66e6245 in QSslSocket::encrypted (this=0xb963efb8) at .moc/release-shared/moc\_qsslsocket.cpp:149  
#17 0xb66f1831 in QSslSocketBackendPrivate::startHandshake (this=0xb96857b8) at ssl/qsslsocket\_openssl.cpp:1404  
#18 0xb66f3070 in QSslSocketBackendPrivate::transmit (this=0xb96857b8) at ssl/qsslsocket\_openssl.cpp:1108  
#19 0xb66e61a8 in QSslSocketPrivate::\_q\_readyReadSlot (this=0xb96857b8) at ssl/qsslsocket.cpp:2205  
#20 0xb66ec0a3 in qt\_static\_metacall (\_a=0xbfbfd4360, \_id=15, \_o=0xb963efb8, \_c=<optimized out>) at .moc/release-shared/moc\_qsslsocket.cpp:98  
#21 QSslSocket::qt\_static\_metacall (\_o=0xb963efb8, \_c=QMetaObject::InvokeMetaMethod, \_id=15, \_a=0xbfbfd4360) at .moc/release-shared/moc\_qsslsocket.cpp:77  
#22 0xb73b46b1 in QMetaObject::activate (sender=0xb940c7d0, m=0xb74faa58, local\_signal\_index=0, argv=0x0) at kernel/qobject.cpp:3547  
#23 0xb7404b25 in QIODevice::readyRead (this=0xb940c7d0) at .moc/release-shared/moc\_qiodevice.cpp:105  
#24 0xb66c7a83 in QAbstractSocketPrivate::canReadNotification (this=0xb96ac1f8) at socket/qabstractsocket.cpp:654  
#25 0xb66b58f9 in QAbstractSocketEngine::readNotification (this=0xb9499c90) at socket/qabstractsocketengine.cpp:168  
#26 0xb66d068b in event (this=0xb96a7e68, e=<optimized out>) at socket/qnativesocketengine.cpp:1151  
#27 QReadNotifier::event (this=0xb96a7e68, e=0xbfbfd47f4) at socket/qnativesocketengine.cpp:1148  
#28 0xb6888ed4 in notify\_helper (e=0xbfbfd47f4, receiver=0xb96a7e68, this=0xb927a468) at kernel/qapplication.cpp:4559  
#29 QApplicationPrivate::notify\_helper (this=0xb927a468, receiver=0xb96a7e68, e=0xbfbfd47f4) at kernel/qapplication.cpp:4531  
#30 0xb688e30d in QApplication::notify (this=0xbfbfd47f4, receiver=0xb96a7e68, e=0xbfbfd47f4) at kernel/qapplication.cpp:4288  
#31 0xb6028b21 in KApplication::notify (this=0xbfbfd4aec, receiver=0xb96a7e68, event=0xbfbfd47f4) at ../kdeui/kernel/kapplication.cpp:311  
#32 0xb739d97e in QCoreApplication::notifyInternal (this=0xbfbfd4aec, receiver=0xb96a7e68, event=0xbfbfd47f4) at kernel/qcoreapplication.cpp:876  
#33 0xb73cff48 in sendEvent (event=0xbfbfd47f4, receiver=<optimized out>) at ../include/QtCore/../../src/corelib/kernel/qcoreapplication.h:231  
#34 socketNotifierSourceDispatch (source=0xb927af20) at kernel/qeventdispatcher\_glib.cpp:110  
#35 0xb59b8cda in g\_main\_context\_dispatch () from /lib/i386-linux-gnu/libglib-2.0.so.0  
#36 0xb59b90e5 in ?? () from /lib/i386-linux-gnu/libglib-2.0.so.0  
#37 0xb59b91c1 in g\_main\_context\_iteration () from /lib/i386-linux-gnu/libglib-2.0.so.0  
#38 0xb73d08e7 in QEventDispatcherGlib::processEvents (this=0xb925c740, flags=...) at kernel/qeventdispatcher\_glib.cpp:426  
#39 0xb6941aaa in QGuiEventDispatcherGlib::processEvents (this=0xb925c740, flags=...) at kernel/qguieventdispatcher\_glib.cpp:204  
#40 0xb739c50d in QEventLoop::processEvents (this=0xbfbfd4a34, flags=...) at kernel/qeventloop.cpp:149  
#41 0xb739c7a9 in QEventLoop::exec (this=0xbfbfd4a34, flags=...) at kernel/qeventloop.cpp:204  
#42 0xb73a1eba in QCoreApplication::exec () at kernel/qcoreapplication.cpp:1148  
#43 0xb6886a74 in QApplication::exec () at kernel/qapplication.cpp:3820  
#44 0xb757a52b in main (argc=3, argv=0xbfbfd4c64) at /build/builddd/quassel-0.8.0/src/common/main.cpp:144